



Updating Camera Firmware- USB


- 1) Turn off your ScanPro before installing PowerScan software.
- 2) Install PowerScan software.
- 3) When software installation completes, turn on ScanPro.
- 4) Navigate to the FirmwareUpdater_Wizard.exe shown below. (C:\Program Files (x86)\PowerScan XXXX\Tools\USB3 Camera\Firmware Update)




- 5) Double click "FirmwareUpdater_Wizard.exe" and the window below will appear.




6) Click "Next" and the window below will appear.




7) Click "Check For New Firmware" and the "Firmware File", "FPGA File", and "XML File" text boxes will be populated as show below.




8) Click "Program Camera" and the warning below will appear.



9) Click "OK" and programming of the camera will begin. First the Firmware, then the FPGA, and lastly the XML. Do not interrupt this process. Be patient. When it is nearly finished the following window will appear as it attempts to verify the update and communicate with the camera.



10) When finished the window will appear as below.




11) Click "Exit" to finish.


12) You may now start PowerScan and use your ScanPro.

Updating Camera Firmware- FireWire


- 1) Turn off your ScanPro before installing PowerScan software.
- 2) Install PowerScan software.
- 3) When software installation completes, turn on ScanPro.
- 4) Navigate to the FLashUpdate.exe shown below. (C:\Program Files (x86)\PowerScan XXXX\Tools\FW Camera\Firmware Update)




- 5) Double click "FlashUpdate.exe" and the window below will appear.



- 6) Click "Begin Flash Update" and the window below will appear.




7) Do not interrupt this process. Be patient. When it is finished the following window will appear.



8) Turn the power switch on the ScanPro off and then on.

9) Click "OK".

10) Then click "Exit"



You may now start PowerScan and use your ScanPro.